

Connexoon Window RTS and Google Assistant

easy set up



Works with
IFTTT



Contents

Connect to IFTTT	3
Register Google Assistant device	5
Activate Google Assistant voice control Applet	6
Create a new Applet	7

Connect to IFTTT

IFTTT

Prior to IFTTT use...

- Ensure Google Assistant has been programmed and is operational.
- Ensure the Connexoon Window RTS device has scenes or ambiances programmed.

Note: Each Connexoon Window RTS user can have a maximum of 8 scenarios (4 modes and 4 ambiances)






1 Download the IFTTT app or access the IFTTT website <https://ifttt.com>


2 Open the IFTTT app and select **Sign up.**

3 Enter your email address, password and select **Sign up.**

4 Select the **lookup icon in the top right to add your Connexoon Window RTS to the IFTTT account.**




- 5 Type “**Connexoon**” in the search bar and click on **Search**.




- 6 Ensure the **Services** tab has been selected in the search results. Select **Connexoon Asia & Oceania**.



- 7 Select **Connect**.




- 8 Enter the email address and password used for your **Connexoon Window RTS login**.



- 9 **Authorise** IFTTT compatibility with your Connexoon Window RTS.



“Open in IFTTT?” pop-up appears. Select **Open** to proceed.

To return to main screen, click the back arrow in the top-left corner and clear the Search field.




Register Google Assistant device


10 On the **Discover** tab, type in “**Google Assistant**” and click on **Search**.
Select **Google Assistant**. Ensure the **Services** tab has been selected.



11 Select **Connect**.




12 Sign in with your **Google Assistant** login details.



13 Allow IFTTT to access your Google Account.

“Open in IFTTT?” pop-up appears.
Select **Open** to proceed.


To return to main screen,
click the back arrow in the
top-left corner and clear
the Search field.




Activate Google Assistant voice control Applet

- Follow the next steps to **activate existing Applets** created by Connexoon Asia & Oceania.
- To **create a new Applet**, move to step 18.



14 Under **Services** on the **My Applets** tab, select **Connexoon Asia & Oceania**.



15 Scroll through the list of pre-defined **Applets** to select the one you wish to **activate**.



16 Select **Learn more** on the Applet chosen to see the services used. Then select **Turn on**.




- 17 Enter the details in the Applet and select **Save**. Your customised Applet has been created.

Choose the **phrase** which will launch the scene or ambiance.

Optional phrases which will also launch the scene or ambiance.

Select the **Connexoon Window RTS scene or ambiance** to be launched.






Create a new Applet


- 18 Open the **My Applets** tab and select **+** in the top right of the page.

- 19 Select **+** this.



- 20 Search and select **Google Assistant**.



- 21** Select the **type of trigger** to activate the Connexoon Window RTS.





- 22** Enter the phrase to trigger your Connexoon Window RTS. Select **Create trigger**.




- 23** Select **+ that**.




- 24** Search for "**Connexoon**". Ensure you select **Connexoon Asia & Oceania**.




25 Select **Launch a Connexoon scenario**.




26 Select the Scenario you wish to launch from the drop-down menu. Select **Create action**.



27 The Applet has been created, select **Finish** to save.



28 The Applet is saved and can be viewed in **My Applets**.



Somfy Pty Limited

Australia

Toll Free 1800 076 639

t: 02 8845 7200

e: somfy.au@somfy.com

New Zealand

Toll Free 0800 276 639

e: somfy.nz@somfy.com

somfy.com.au

somfy.co.nz



Find us on Facebook



Follow us on Instagram



Subscribe to us on YouTube